

PAL API Reference

Generated from public `Protocol` declarations and source docstrings. Each description is maintained beside its source signature. Regenerate with `python Documentation/generators/generate_api_reference.py` ; use `--check` to detect drift. Consult the PAL Guide for worked usage and Architecture and Design for implementation rationale.

Axis shorthand: `...` after an X/x-specific name includes its Y/y and Z/z variants. Each variant remains a separate callable or property.

Factories and utilities

Function	Description
<code>FastMode()</code>	Select PAL fast mode before constructing any PAL object or window; the process-wide mode cannot be changed after construction.
<code>Seed(seed)</code>	Seed PAL's shared random-number stream; repeatability also depends on the sequence of random calls.
<code>Random()</code>	Draw a uniform random value from PAL's shared random-number stream.
<code>RandInt(max)</code>	Draw an integer from PAL's random stream in the supported range below the positive bound <code>max</code> .
<code>AwaitWindows(timeout=30)</code>	Wait for PAL windows that are still initializing; raises if a window exits early or initialization times out.
<code>ColorScale(colors, value)</code>	Map a scalar value to an RGB color by interpolating through the supplied color scale.
<code>NewIList()</code>	Create an empty PAL integer list usable from Python and supported compiled functions.
<code>MooreHood(dim, excludeCenter=False)</code>	Build relative integer offsets for a Moore neighborhood in <code>dim</code> dimensions; optionally exclude the center offset.
<code>VonNeumannHood(dim, excludeCenter=False)</code>	Build relative integer offsets for a Von Neumann neighborhood in <code>dim</code> dimensions; optionally exclude the center offset.
<code>CircleHood(dim, rad, excludeCenter=False)</code>	Build relative integer offsets within radius <code>rad</code> in <code>dim</code> dimensions; optionally exclude the center offset.
<code>NewMultinomial(other=None)</code>	Create a PAL multinomial/binomial sampler, optionally reusing configuration from <code>other</code> .
<code>NewGrid(dimensions, dtype)</code>	Create a typed lattice grid with the requested dimensions and element dtype.
<code>NewAgentGrid(dimensions, numAgentProps=0, isStackable=False)</code>	Create a grid for individual agents; <code>numAgentProps</code> sets the number of per-agent properties and <code>isStackable</code> controls whether multiple agents may occupy a site.

Function	Description
<code>NewPopGrid(dimensions, dtype=np.int64)</code>	Create a lattice of integer population counts; <code>dtype</code> explicitly selects <code>uint8</code> , <code>uint16</code> , <code>uint32</code> , or <code>int64</code> (default) field storage, with <code>int16</code> , <code>int32</code> , <code>int64</code> , or <code>int64</code> deltas respectively.
<code>NewPDEgrid(dimensions)</code>	Create a lattice-backed scalar field for numerical transport operations.

Multinomial

Kind	Declaration	Description
method	<code>Binomial(self, n: int, p: float) -> int</code>	Draw a binomial sample with <code>n</code> trials and success probability <code>p</code> using this sampler's configured random stream.
method	<code>Setup(self, n: int)</code>	Configure the sampler for <code>n</code> trials before repeated sampling.
method	<code>Sample(self, p: float) -> int</code>	Draw a binomial sample using the sampler's current configuration and success probability <code>p</code> .

IList

Kind	Declaration	Description
method	<code>__len__(self) -> int</code>	Return the number of integers currently stored in the list.
method	<code>__getitem__(self, index: int) -> int</code>	Return the integer stored at the given list position.
method	<code>Append(self, i: int)</code>	Append integer <code>i</code> to the end of the list.
method	<code>Clear(self)</code>	Remove all values from the list.
method	<code>Random(self) -> int</code>	Return a randomly selected value from the list; the list must be nonempty.
method	<code>Shuffle(self)</code>	Shuffle the list in place using PAL's random stream.
method	<code>All(self) -> np.ndarray</code>	Return a detached NumPy array containing the list values.
method	<code>Iter(self) -> np.ndarray</code>	Iterate over the current list values without creating the detached copy returned by <code>All()</code> .

AgentGrid

Kind	Declaration	Description
method	<code>__len__(self) -> int</code>	Return the number of living agents in the grid.

Kind	Declaration	Description
property	<code>xDim...(self) -> int</code>	Number of lattice sites along x; corresponding Y/Z variants use the same contract.
property	<code>nDims(self) -> int</code>	Number of spatial dimensions.
property	<code>wrapX...(self) -> bool</code>	Whether x uses periodic boundary wrapping; corresponding Y/Z variants use the same contract.
method	<code>Box(self, x1: int, x2: int, y1: int=None, y2: int=None, z1: int=None, z2: int=None)</code>	Iterate lattice coordinates in the half-open rectangular region $[x1, x2) \times [y1, y2) \times [z1, z2)$; omit unused axes in lower dimensions.
method	<code>Hood(self, hood, x: int, y: int=None, z: int=None, *, unroll: bool=False)</code>	Apply relative neighborhood offsets at a lattice coordinate, respecting wrapped and nonwrapped boundaries. <code>unroll=True</code> enables compiled-loop expansion where supported.
method	<code>GetPop(self) -> int</code>	Return the number of living agents in the grid.
method	<code>Alive(self, agent: int) -> bool</code>	Return whether agent currently identifies a living agent.
method	<code>NewAgentSQ(self, x: int, y: int=-1, z: int=-1) -> int</code>	Create an agent at the center of a lattice site specified by integer coordinates or a supported linear site index.
method	<code>NewAgent(self, x: float, y: float=-1.0, z: float=-1.0) -> int</code>	Create an agent at the supplied continuous spatial coordinates.
method	<code>Dispose(self, agent: int)</code>	Remove a living agent from the grid; its handle must not be used as a live agent afterward.
method	<code>I(self, agent: int) -> int</code>	Return the linear lattice-site index containing the agent.
method	<code>XSQ...(self, agent: int) -> int</code>	Return the agent's integer x site coordinate; corresponding Y/Z variants use the same contract.
method	<code>X...(self, agent: int) -> float</code>	Return the agent's continuous x coordinate; corresponding Y/Z variants use the same contract.
method	<code>__getitem__(self, key) -> float</code>	Read a supported per-agent property value.
method	<code>__setitem__(self, key, value: float)</code>	Set a supported per-agent property value for the selected agent/property key.
method	<code>ToI(self, x: int, y: int=-1, z: int=-1) -> int</code>	Convert lattice coordinates to the corresponding linear site index.
method	<code>ItoX...(self, i: int) -> int</code>	Convert a linear site index to its x coordinate; corresponding Y/Z variants use the same contract.
method	<code>InWrapSQX...(self, value: int) -> int</code>	Wrap an integer x site coordinate when x is periodic; corresponding Y/Z variants use the same contract.
method	<code>InWrapX...(self, value: float) -> float</code>	Wrap a continuous x coordinate when x is periodic; corresponding Y/Z variants use the same contract.

Kind	Declaration	Description
method	<code>DispWrapX(self, x1: float, x2: float) -> float</code>	Return the shortest signed x displacement under periodic wrapping.
method	<code>DispWrapY(self, y1: float, y2: float) -> float</code>	Return the shortest signed y displacement under periodic wrapping.
method	<code>DispWrapZ(self, z1: float, z2: float) -> float</code>	Return the shortest signed z displacement under periodic wrapping.
property	<code>counts(self) -> object</code>	Read-only occupancy counts for lattice sites; change occupancy through agent creation, movement, and disposal methods.
method	<code>LastAgent(self, x: int, y: int=-1, z: int=-1) -> int</code>	Return the last agent handle at the specified lattice site, or the empty-site sentinel when none is present.
method	<code>MoveSQ(self, agent: int, x: int, y: int=-1, z: int=-1)</code>	Move an agent to a lattice site specified by integer coordinates or a supported linear site index.
method	<code>Move(self, agent: int, x: float, y: float=-1.0, z: float=-1.0)</code>	Move an agent to continuous coordinates; use <code>MoveSQ</code> when movement should target a lattice site.
method	<code>AgentsAt(self, x: int, y: int=-1, z: int=-1)</code>	Return the agent handle or handles occupying the specified lattice site.
method	<code>AgentsInRadius(self, rad: float, x: float, y: float=-1.0, z: float=-1.0, *, exclude: int=None)</code>	Return agents within radius <code>rad</code> of a continuous position; <code>exclude</code> can omit one agent from the results.
method	<code>All(self, shuffle: bool=False) -> np.ndarray</code>	Return a snapshot of living agent handles, optionally shuffled. The snapshot fixes membership, not later world state or occupancy queries.

Grid

Kind	Declaration	Description
method	<code>__len__(self) -> int</code>	Return the number of lattice sites.
method	<code>__getitem__(self, key)</code>	Read the value or state selected by the supported index or coordinate key.
method	<code>__setitem__(self, key, value)</code>	Assign the value or state selected by the supported index or coordinate key.
property	<code>xDim...(self) -> int</code>	Number of lattice sites along x; corresponding Y/Z variants use the same contract.
property	<code>nDims(self) -> int</code>	Number of spatial dimensions.

Kind	Declaration	Description
property	<code>wrapX...(self) -> bool</code>	Whether x uses periodic boundary wrapping; corresponding Y/Z variants use the same contract.
method	<code>Box(self, x1: int, x2: int, y1: int=None, y2: int=None, z1: int=None, z2: int=None)</code>	Iterate lattice coordinates in the half-open rectangular region $[x1, x2) \times [y1, y2) \times [z1, z2)$; omit unused axes in lower dimensions.
method	<code>Hood(self, hood, x: int, y: int=None, z: int=None, *, unroll: bool=False)</code>	Apply relative neighborhood offsets at a lattice coordinate, respecting wrapped and nonwrapped boundaries. <code>unroll=True</code> enables compiled-loop expansion where supported.
method	<code>ToI(self, x: int, y: int=-1, z: int=-1) -> int</code>	Convert lattice coordinates to a linear site index.
method	<code>ItoX...(self, i: int) -> int</code>	Convert a linear site index to its x coordinate; corresponding Y/Z variants use the same contract.
method	<code>InWrapX...(self, value: int) -> int</code>	Wrap an x coordinate when x is periodic; otherwise return it unchanged; corresponding Y/Z variants use the same contract.

PopGrid

Kind	Declaration	Description
method	<code>__len__(self) -> int</code>	Return the number of lattice sites.
property	<code>xDim...(self) -> int</code>	Number of lattice sites along x; corresponding Y/Z variants use the same contract.
property	<code>nDims(self) -> int</code>	Number of spatial dimensions.
property	<code>wrapX...(self) -> bool</code>	Whether x uses periodic boundary wrapping; corresponding Y/Z variants use the same contract.
method	<code>Box(self, x1: int, x2: int, y1: int=None, y2: int=None, z1: int=None, z2: int=None)</code>	Iterate lattice coordinates in the half-open rectangular region $[x1, x2) \times [y1, y2) \times [z1, z2)$; omit unused axes in lower dimensions.
method	<code>Hood(self, hood, x: int, y: int=None, z: int=None, *, unroll: bool=False)</code>	Apply relative neighborhood offsets at a lattice coordinate, respecting wrapped and nonwrapped boundaries. <code>unroll=True</code> enables compiled-loop expansion where supported.
method	<code>ToI(self, x: int, y: int=-1, z: int=-1) -> int</code>	Convert lattice coordinates to a linear site index.
method	<code>ItoX...(self, i: int) -> int</code>	Convert a linear site index to its x coordinate; corresponding Y/Z variants use the same contract.

Kind	Declaration	Description
method	<code>InWrapX...(self, value: int) -> int</code>	Wrap an x coordinate when x is periodic; otherwise return it unchanged; corresponding Y/Z variants use the same contract.
method	<code>__getitem__(self, key) -> int</code>	Return the integer population count at the selected site.
method	<code>__setitem__(self, key, value: int)</code>	Set the population count at the selected site immediately; this is distinct from queueing a delta with <code>Add()</code> .
method	<code>Add(self, value: int, x: int, y: int=-1, z: int=-1)</code>	Queue a signed population-count delta at a site; call <code>Update()</code> to apply pending deltas.
method	<code>Update(self)</code>	Apply queued population-count deltas to the current counts.
method	<code>Reset(self)</code>	Clear population counts and any pending deltas.
method	<code>GetPop(self) -> int</code>	Return the total population summed across all lattice sites.
method	<code>All(self) -> np.ndarray</code>	Return linear indices of sites whose population count is nonzero.

PDEgrid

Kind	Declaration	Description
method	<code>__len__(self) -> int</code>	Return the number of lattice sites.
property	<code>xDim...(self) -> int</code>	Number of lattice sites along x; corresponding Y/Z variants use the same contract.
property	<code>nDims(self) -> int</code>	Number of spatial dimensions.
property	<code>wrapX...(self) -> bool</code>	Whether x uses periodic boundary wrapping; corresponding Y/Z variants use the same contract.
method	<code>Box(self, x1: int, x2: int, y1: int=None, y2: int=None, z1: int=None, z2: int=None)</code>	Iterate lattice coordinates in the half-open rectangular region $[x1, x2) \times [y1, y2) \times [z1, z2)$; omit unused axes in lower dimensions.
method	<code>Hood(self, hood, x: int, y: int=None, z: int=None, *, unroll: bool=False)</code>	Apply relative neighborhood offsets at a lattice coordinate, respecting wrapped and nonwrapped boundaries. <code>unroll=True</code> enables compiled-loop expansion where supported.
method	<code>ToI(self, x: int, y: int=-1, z: int=-1) -> int</code>	Convert lattice coordinates to a linear site index.
method	<code>ItoX...(self, i: int) -> int</code>	Convert a linear site index to its x coordinate; corresponding Y/Z variants use

Kind	Declaration	Description
		the same contract.
method	<code>InWrapX...(self, value: int) -> int</code>	Wrap an x coordinate when x is periodic; otherwise return it unchanged; corresponding Y/Z variants use the same contract.
method	<code>__getitem__(self, key) -> float</code>	Return the field value at the selected site.
method	<code>__setitem__(self, key, value: float)</code>	Set the field value at the selected site immediately; this is distinct from queueing a change with <code>Add()</code> .
method	<code>Add(self, value: float, x: int, y: int=-1, z: int=-1)</code>	Queue a field-value delta at a site; call <code>Update()</code> to apply pending changes.
method	<code>Update(self)</code>	Apply queued field changes to the current field.
method	<code>Reset(self)</code>	Clear the field and any pending changes.
method	<code>SetTimeSpaceStep(self, dt: float, dx: float, dy: float=1.0, dz: float=1.0)</code>	Set the temporal step <code>dt</code> and spatial steps <code>dx</code> , <code>dy</code> , and <code>dz</code> used by numerical transport methods.
method	<code>Dx...(self) -> float</code>	Return the configured spatial step along x; corresponding Y/Z variants use the same contract.
method	<code>Dt(self) -> float</code>	Return the configured time step.
method	<code>Diffusion(self, rateConstant: float, xMinBC=None, xMaxBC=None, yMinBC=None, yMaxBC=None, zMinBC=None, zMaxBC=None)</code>	Apply scalar-coefficient diffusion using the configured grid spacing and optional per-face boundary conditions.
method	<code>DiffusionMask(self, rateConstant: float, mask=None, xMinBC=None, xMaxBC=None, yMinBC=None, yMaxBC=None, zMinBC=None, zMaxBC=None)</code>	Diffuse across unmasked interfaces, with optional boundary values on active domain faces; masked cells remain impermeable.
method	<code>DiffusionField(self, rateConstants, xMinBC=None, xMaxBC=None, yMinBC=None, yMaxBC=None, zMinBC=None, zMaxBC=None)</code>	Apply diffusion with spatially varying rate constants and optional boundary conditions.
method	<code>DiffusionInterfaces(self, rateConstantsX, rateConstantsY=None, rateConstantsZ=None, xMinBC=None, xMaxBC=None, yMinBC=None, yMaxBC=None, zMinBC=None, zMaxBC=None)</code>	Apply diffusion using rate constants defined on grid interfaces; separate arrays may specify x, y, and z interfaces.
method	<code>DiffusionADI(self, rateConstant: float, xMinBC=None, xMaxBC=None, yMinBC=None, yMaxBC=None, zMinBC=None, zMaxBC=None)</code>	Apply diffusion using an alternating-direction implicit method.

Kind	Declaration	Description
method	<code>DiffusionRadialCircle(self, rateConstant: float, outerBC=None)</code>	Apply radial diffusion on a circular domain with an optional outer boundary condition.
method	<code>DiffusionRadialSphere(self, rateConstant: float, outerBC=None)</code>	Apply radial diffusion on a spherical domain with an optional outer boundary condition.
method	<code>Advection(self, vx: float, vy: float=0.0, vz: float=0.0, xMinBC=None, xMaxBC=None, yMinBC=None, yMaxBC=None, zMinBC=None, zMaxBC=None)</code>	Apply advection using a constant velocity vector and optional per-face boundary conditions.
method	<code>AdvectionField(self, xVels, yVels=None, zVels=None, xMinBC=None, xMaxBC=None, yMinBC=None, yMaxBC=None, zMinBC=None, zMaxBC=None)</code>	Apply advection using spatially varying velocity fields.
method	<code>AdvectionInterfaces(self, xVels, yVels=None, zVels=None, xMinBC=None, xMaxBC=None, yMinBC=None, yMaxBC=None, zMinBC=None, zMaxBC=None)</code>	Apply advection using velocity values defined on grid interfaces.

PixWindow visualization

```
StartPixWindow(xDim, yDim, scale=1, title='PAL', headless=False) -> tuple[Pix, PixWindow]
```

Create a pixel-based visualization window and its writable pixel buffer.

Kind	Declaration	Description
method	<code>IsOpen(self) -> bool</code>	Return whether the window is currently open.
method	<code>Update(self)</code>	Publish the current pixel buffer as a frame.
method	<code>Save(self, path: str, block=False)</code>	Save the current pixel buffer to an image file; block controls whether to wait for completion.
method	<code>StartGif(self, path: str, delay=100)</code>	Start recording frames to a GIF at path with the requested frame delay in milliseconds.
method	<code>AddGifFrame(self, block=False)</code>	Append the current pixel buffer as a GIF frame; optionally wait for the frame operation to finish.
method	<code>StopGif(self)</code>	Finish GIF recording and write the accumulated animation.
method	<code>Close(self)</code>	Close the window and release its rendering resources.

OpenGLWindow visualization

```
StartOpenGLWindow(xDim, yDim, zDim=None, width=800, height=800, title='PAL', headless=False) ->
```

```
tuple[OpenGLDraw, OpenGLWindow]
```

Create an OpenGL visualization window for 2D or 3D drawing.

Kind	Declaration	Description
method	<code>Update(self)</code>	Publish the accumulated drawing primitives as the next frame.
method	<code>IsOpen(self) -> bool</code>	Return whether the window is currently open.
method	<code>StartGif(self, path, delay=100)</code>	Start recording rendered frames to a GIF with the requested frame delay in milliseconds.
method	<code>AddGifFrame(self, block=False, timeout=30)</code>	Capture the current scene as a GIF frame; optionally wait for completion.
method	<code>StopGif(self, timeout=30)</code>	Finish GIF recording and write the animation.
method	<code>Borders(self, width, color)</code>	Draw persistent outline borders around the model domain.
method	<code>Camera(self, x, y, z, yaw=None, pitch=None)</code>	Set the 3D camera position and optional yaw/pitch angles.
method	<code>Clear(self)</code>	Clear accumulated drawing primitives for the next frame.
method	<code>Background(self, color)</code>	Set the background color used when rendering frames.
method	<code>Save(self, path: str, block=False)</code>	Save the currently published scene to an image file; block controls whether to wait for completion.
method	<code>Close(self)</code>	Close the window and release rendering resources.

The `OpenGLWindow` table follows its source Protocol, which also contains method implementations; repeated declarations are listed once. `OpenGLDraw` is a compiled primitive collector, while the returned window handles rendering and output. Consult the [PAL Guide](#) for which object to use in Python and compiled drawing code.

Pix drawing buffer

Kind	Declaration	Description
method	<code>__setitem__(self, key, color)</code>	Write a packed RGB color to a pixel by (x, y) coordinates or a linear pixel index.
method	<code>xDim(self)</code>	Return the pixel buffer width.
method	<code>yDim(self)</code>	Return the pixel buffer height.
method	<code>ToI(self, x, y)</code>	Convert pixel coordinates (x, y) to a linear index.
method	<code>ItoX(self, i)</code>	Convert a linear pixel index to its x coordinate.
method	<code>ItoY(self, i)</code>	Convert a linear pixel index to its y coordinate.

Kind	Declaration	Description
method	<code>__len__(self)</code>	Return the total number of pixels.

OpenGLDraw primitive collector

Kind	Declaration	Description
method	<code>clear(self)</code>	Discard all primitives accumulated for the next frame.
method	<code>circle(self, rad, color, x, y, z=0.0)</code>	Add a circle centered at (x, y, z) with radius rad and color.
method	<code>Box(self, xLen, color, x, y, z=0.0, yLen=-1.0, zLen=-1.0)</code>	Add a box centered at (x, y, z); negative side lengths default to xLen.
method	<code>BoxSQ(self, color, x, y, z=0.0)</code>	Add a unit box centered on lattice site (x, y, z).
method	<code>Line(self, width, color, x1, y1, x2, y2, z1=0.0, z2=0.0)</code>	Add a line segment between endpoints with the requested width and color.

Scope and validation

This reference lists public Protocol signatures, not internal safe/fast jitclass methods. A signature does not capture every runtime overload, indexing form, or validation rule. See the PAL Guide and executable tests. Visualization constructors and window Protocol methods are included; Pix buffer and OpenGLDraw method signatures are also included; consult the PAL Guide for behavior.